

YARN USAGE

	Teddy	Cosy
3-4 year:	350 g	50 g
5-6 year:	450 g	50 g
7-8 year:	500 g	50 g
9-10 year:	600 g	50 g
11-12 year:	650 g	50 g

MATERIALS

Buttons 4 pcs Marker Stitch holder

Circular Needles: 3,0 mm and 3,5 mm

60 and 80 cm

Gauge: 19 stitch x 33 rows in Stockinette Stitch on needle 3,5 mm = 10 x 10 cm

The given amounts of yarn are for guidance only

FINAL MEASUREMENTS

Size. 3-4 yrs (5-6 yrs) 7-8 yrs (9-10 yrs) 11-12 yrs		
Chest	63 (65) 72 (78) 84 cm.	
Length	37 (42) 45 (48) 50 cm.	
Arm Length	23 (28) 32 (36) 39 cm.	

DEFINITIONS

Decrease At the beginning of the row; knit

2 stitches together through the back

loop.

At the end of the row; knit 2 stitches

together.

Increase Make an increase in the loop between

the stitches, knit it on the right side and

purl on the wrong side.

Buttenhole Bind off 2 stitches. On the next row,

cast on 2 stitches over the bound-off

stitches.

(..) Indicates quantities for the 7 sizes *...* What is between is repeated

...* What is between is repeated throughout the row

Teddy

Soft like a dream and a yarn many have been longing for, to be used for knitting and crocheting baby ware, teddies and blankets. Perfect for knitted teddy jackets and

blankets. Perfect for knitted teddy jackets and sweaters that are wonderful to wear. A "fluffy" yarn, that doesn't require any special techniques or stitches to get a nice and chunky result.

100% Polyester, 50 g/65 m.

Cosy

The thread is quite lightspun, soft and with a very special elasticity, which preserves the knit beautiful. The Cosy yarn is a bit vintage in its expression – warm, strong and even breathable.

60% Cotton/40% Acrylic, 50 g/100 m.

Go handmade

TESTED AND APPROVE

2

GUIDE:

- Knit on a circular needle up to the armhole, where the work is divided
- The outer side of the pocket is knit back and forth and then sewn together with the front piece.
- The sleeves are knit back and forth and then sewn in.
- Stitches are picked up at the neckline

SWEATER LOUIE

3-4 yrs (5-6 yrs) 7-8 yrs (9-10 yrs) 11-12 yrs

BACK PIECE AND FRONT PIECE

Cast on 120 (124) 136 (148) 160 stitches on a 3.0 mm needle (60 or 80 cm) using Teddy yarn. Work in rib in the round, *knit 1, purl 1*. Knit 3 rounds.

Place a marker at the beginning of the round and another marker after **60 (62) 68 (74) 80** stitches. The first marker is the left side of the work. The second marker is the right side of the work.

Switch to a 3.5 mm needle (60 or 80 cm).
Continue in stocking stitch for the remainder of the work

When the work measures **5.5 (6.5) 6.5 (7.5) 8.5** cm, start the pocket.

POCKET

Knit 12 (12) 13 (15) 17 stitches, place a marker, knit 36 (38) 42 (44) 46 stitches, place a marker, knit the rest of the round.

The stitches between the markers are for the pocket.

Continue with the pocket. Work back and forth in stocking stitch.

Purl back on the pocket stitches from the wrong side. Simultaneously, cast on 1 new stitch on each side, these are edge stitches.

There are a total of **38 (40) 44 (46) 48** stitches on the needle.

On the next row, from the right side, make 1 decrease inside the edge stitch on each side. Repeat the decreases every 2nd row an additional 3 (3) 4 (1) 3 times.

Then, repeat the decreases every 4th row 5 (6) 6 (9) 8 times.

After the last decrease, from the right side, knit 3 rows in stocking stitch.

On the last row from the wrong side, bind off the edge stitches on both sides. There are a total of 18 (18) 20 (22) 22 stitches left on the needles.

Place the stitches on a stitch holder.

THE POCKET'S INNER SIDE

On the wrong side, pick up **36 (38) 42 (44) 46** stitches with a 3.5 mm needle for the inside of the pocket.

Pick up stitches, **4.5** (**5.5**) **5.5** (**6.5**) **7.5** cm from the cast-on edge, at the bottom.

Knit 3 rows back and forth.

Continue by knitting the inside of the pocket together with the front and back pieces.

Knit the first 12 (12) 13 (15) 17 stitches of the front piece, knit 36 (38) 42 (44) 46 stitches from the inside of the pocket, then knit the remaining stitches from the front piece and finally the stitches from the back piece. Continue knitting in the round in stocking stitch until

On the next round, knit the front of the pocket together with the front piece.

it matches the height of the pocket.

Knit **21 (22) 24 (26) 29** stitches from the front piece. Place the pocket's **18 (18) 20 (22) 22** stitches on a 3.5 mm needle.

Hold the needle parallel to the circular needle and knit the pocket's outer stitches together with the pocket's inner stitches.

Knit the entire round.

BACK AND FRONT PIECES - CONTINUED

Continue in stocking stitch in the round.

Knit until the work measures 20 (24) 26 (29) 30 cm. Divide the work for the armholes.

Knit 60 (62) 68 (74) 80 stitches.

Place these stitches on a stitch holder; this is the front piece.

BACK PIECE

Continue with the remaining 60 (62) 68 (74) 80 stitches for the back piece.

Cast on 1 new stitch on each side; these are edge stitches.

There are a total of **62 (64) 70 (76) 82** stitches on the needle.

The first row is the right side.

Work in stocking stitch back and forth.

Knit until the work measures 36 (41) 44 (47) 49 cm.

Neck and Shoulder Shaping:

On the right side, bind off 9 (10) 11 (12) 14 stitches at the beginning of the row for the right shoulder, knit 12 (12) 13 (15) 16 stitches,

bind off 20 (20) 22 (22) 22 stitches at the center for the neck.

knit the rest of the row.

Each side is worked separately.

Left side:

Wrong side: Bind off **9 (10) 11 (12) 14** stitches for the shoulder, knit the row.

Right side: Bind off 2 stitches for the neck, knit the

Wrong side: Bind off the remaining 10 (10) 11 (13) 14 stitches for the shoulder

Riaht side:

Wrong side: Bind off 2 stitches for the neck, knit the row.

Right side: Bind off the remaining 10 (10) 11 (13) 14 stitches for the shoulder.

FRONT PIECE

Place the stitches from the front piece on a 3.5 mm needle (60 cm).

The first row is the right side.

Cast on 1 new stitch on each side for edge stitches. There are a total of **62 (64) 68 (74) 80** stitches on the needle.

Work in stocking stitch back and forth.

Slit:

On the first row from the right side, bind off the 4 center stitches and work each side separately. There are a total of 29 (30) 32 (35) 38 stitches on each side.

Right side:

When the work measures 31 (36) 39 (41) 43 cm, start neck shaping.

Bind off from the right side every 2nd row for 5-2-1-1-1 (5-2-1-1-1) 5-2-1-1-1 (5-2-1-1-1) 5-2-1-1-1 stitches

When the work measures 36 (41) 44 (47) 49 cm, start shoulder shaping.

Bind off from the wrong side every 2nd row for 9-10 (10-10) 11-11 (12-13) 14-14 stitches.

Left side:

When the work measures 31 (36) 39 (41) 43 cm, start neck shaping.

Bind off from the wrong side every 2nd row for 5-2-1-1-1 (5-2-1-1-1) 5-2-1-1-1 (5-2-1-1-1) 5-2-1-1-1 stitches.

When the work measures **37 (41) 44 (48) 52** cm, start shoulder shaping.

Bind off from the right side every 2nd row for 9-10 (10-10) 11-11 (12-13) 14-14 stitches.

Sew the shoulder seams together.

NECKLINE

From the right side of the work, using a 3.5 mm needle (60 cm) and Teddy yarn, pick up stitches evenly around the neckline.

Pick up 63 (63) 69 (69) 69 stitches.

Work ribbing by knitting 1 stitch and purling 1 stitch alternately within the edge stitch on each side.

Knit for 6 (6.5) 6.5 (7) 7 cm, with the last row being a right side row.

Place the stitches onto a stitch holder.

For the left neckline:

Using a 3.0 mm needle and Teddy yarn, pick up stitches evenly along the edge of the neckline. Begin at the right side at the top of the neckline. Continue working ribbing by knitting 1 stitch and purling 1 stitch alternately within the edge stitch on each side.

Knit for **7** rows, with the last row being from the wrong side.

Bind off in ribbing from the right side.

For the right neckline:

Using a 3.0 mm needle and Teddy yarn, pick up stitches evenly along the edge of the neckline.

Start at the right side at the bottom of the neckline.

Work ribbing by knitting 1 stitch and purling 1 stitch alternately within the edge stitch on each side.

Knit for 3 rows.

Create 4 buttonholes.

Position the bottom buttonhole approximately 2 cm from the bound-off edge at the bottom of the neckline.

Place the top buttonhole about 1 cm below the neckline

Space the remaining buttonholes evenly.

Knit a total of **7** rows, with the last row being from

the wrong side. Bind off in ribbing from the right side.

Continuing the neckline:

Starting from the right side, with a 3.0 mm needle (60 cm) and Cosy yarn, pick up stitches at the top of the neckline.

Begin on the upper side of the right neckline.

Next, transfer the stitches from the stitch holder onto a 3.0 mm needle and knit on the right side.

Finally, pick up stitches on the upper side of the left neckline.

The total number of stitches should be odd.
Knit 3 rows of ribbing by alternating between knitting 1 stitch and purling 1 stitch within the edge stitch on each side.
Bind off in ribbing.

Secure the edges at the bottom by sewing them together.

Attach buttons to the left front edge.

SLEEVES X 2

Cast on **35 (37) 37 (37) 39** stitches using a 3.0 mm needle in Cosy yarn. Work ribbing by knitting 1 stitch and purling 1 stitch within the edge stitch on each side. The first and last rows are wrong side rows.

Knit 3 rows.

Switch to a 3.5 mm needle and Teddy yarn. Continue in stockinette stitch within the edge stitch on each side.

On the first row, increase 3 (3) 3 (5) 5 stitches evenly distributed

There are a total of 38 (40) 40 (42) 44 stitches on the needle.

When the work measures 2 cm, begin the increases.

Ages 3-4: Increase 1 stitch within the edge stitch every 4th row, twice.

Then, increase every **6**th row, **9** times. There are a total of **60** stitches on the needle.

Ages 5-6: Increase 1 stitch within the edge stitch every **6th** row, **7** times.

Then, increase every 8th row, 5 times.

There are a total of 64 stitches on the needle.

Ages 7-8: Increase 1 stitch within the edge stitch every **6**th row, **6** times.

Then, increase every 8th row, 7 times.

There are a total of 66 stitches on the needle.

Ages 9-10: Increase 1 stitch within the edge stitch every 6th row, 4 times.

Then, increase every 8th row, 10 times.
There are a total of 70 stitches on the needle.

Ages 11-12: Increase 1 stitch within the edge stitch every 6th row, 5 times.

Then, increase every 8th row, 10 times.

There are a total of **74** stitches on the needle.

When the work measures **23 (28) 32 (36) 39** cm, bind off from the right side.

RIBBED EDGE ON THE POCKET

Right side: Start from the top.

Pick up stitches evenly along the edge using a 3.0 mm needle and Cosy yarn.

The number of stitches should be odd.

Work ribbing by knitting 1 stitch and purling 1 stitch within the edge stitch on each side.

Knit 3 rows.

Bind off in ribbing.

Left side: Start from the bottom. Pick up stitches as done on the right side. Work ribbing as in the right side ribbing.

Sew the ribbed edges onto the front piece. Attach and sew the sleeves together.

Good to know

Needle Size & Tension

Knitters knit very differently: some knit with a needle size 2,0 mm and obtain the same size of design quality as a person who knits with a needle size 4,0 mm. We owe this knowledge to the team of knitters who join us. The key to knit a specific size is a lot about the knitting style/hands/skills, rather than the size of needles. Therefore, we will recommend a range of needle sizes.



IOT24082023

Go handmade quality design in a unique style